

# Quick Reference Guide

## Plesk for Linux

<b>If you want to:</b>	<b>Go here:</b>
Set up a client	Select <b>Clients</b> Select <b>Add New Client Account</b>
Set up a domain	Select <b>Domains</b> Select <b>Add New Domain</b> Select a specific client name
Set up email	Select <b>Domains</b> Select the applicable domain from the list Select <b>Mail</b> Select <b>Add New Mail Name</b>
Set/Change DNS on a domain	<b>Domains</b> Select the applicable domain from the list Select <b>DNS Settings</b>
Create a CSR for an SSL Certificate	Select <b>Domains</b> Select the applicable domain from the list Select <b>Certificates</b> Select <b>Add New Certificate</b>
Add/Update Plesk software	Select <b>Server</b> Select <b>Updater</b> Select the applicable Release from the list
Add an IP to the server:	<b>Prerequisite</b> (Request additional IP from the Host Control Center)  Select <b>Server</b> Select <b>IP Addresses</b> Select <b>Add New IP Address</b>
Assign an IP to a Client	Select <b>Clients</b> Select a specific client name Select <b>IP Pool</b> Select <b>Add New IP Address</b>

Assign an IP to a domain	<p><b>Prerequisite</b> (You must assign the IP to the Client first)</p> <p>Select <b>Domains</b> Select the applicable domain from the list</p> <p>Select <b>Setup</b> Select the IP Address from the dropdown menu [The IP must be set as Exclusive for SSLs]</p>
Change a Client password	<p>Select <b>Clients</b> Select a specific client name</p> <p>Select <b>Edit</b></p>
Change a Domain/FTP Login	<p>Select <b>Domains</b> Select the applicable domain from the list</p> <p>Select <b>Setup</b></p>
Change a Domain/FTP password	<p>Select <b>Domains</b> Select the applicable domain from the list</p> <p>Select <b>Setup</b></p>
Turn on/off a client	<p>Select <b>Clients</b> Select a specific client name</p> <p>Select <b>Switch Off/Switch On</b></p>
Turn on/off a domain	<p>Select <b>Domains</b> Select the applicable domain from the list</p> <p>Select <b>Switch Off/Switch On</b></p>
Back up a domain	<p>Select <b>Domains</b> Select the applicable domain from the list</p> <p>Select <b>Create Backup</b></p>
Check the Mail Queue	<p>Select <b>Server</b> Select <b>Mail</b> Select the tab <b>Mail Queue</b></p>
Change a client's permissions	<p>Select <b>Clients</b> Select a specific client name</p> <p>Select <b>Permissions</b></p>
Change the Plesk Password	<p>Select <b>Server</b> Select <b>Change Password</b></p>
Set default DNS settings	<p>Select <b>Server</b> Select <b>DNS Settings</b></p>

Update Stats Password	Select <b>Domains</b> Select the applicable domain from the list Select <b>Protected Directories</b> Select <b>/Plesk-stat</b> Select the applicable user name
Create an Shared/Exclusive IP	Select <b>Server</b> Select <b>IP Addresses</b> Select Specific IP Select Shared/Exclusive